
Creation of Windows 10 media for OS Installation


Download Windows 10 media creation tool from MS site. Once you download the same, do run it. It will select upgrade this PC by default. Do not select this option, select create media for another PC. Do not select create USB drive instead of do download the ISO image file.



Once ISO image is downloaded. You may create bootable Windows 10 media pen drive using "rufus" . Link to download : https://rufus.ie/en_US/

Creation of Windows 10 media for OS Installation

Run "rufus" tool and select the Windows 10 ISO image as per below snap.



Once ISO image is downloaded. You may create bootable Windows 10 media pen drive using "rufus" . Link to download : https://rufus.ie/en_US/

Windows 10 installation process

After pen drive creation is completed, you can boot from pen drive. Select first boot device is pen drive then it will boot from pen drive.

- Boot into bios by pressing f2 or delete.
- Under main/ advance tab enable one time boot menu f12...
- Under security set supervisor password. Set password.
- Under Boot menu disable the secure boot.
- · Save and exit by pressing 10.
- Restart the system and keep on tapping f12 and select the bootable pen drive.
- Follow on screen instruction.
- Need to follow on screen instruct to get Windows 10 install.
- You may delete entire partition as per your requirement or delete only C drive.
- Once installation completed enable the secure boot in bios.